

Hrvatske kodne stranice																		
Znak	Simb. ime	MS DOS CP 852		Windows CP 1250				ISO 8859-2				ASCII / CROSCII				ISO 8859-1 ekvivalent		HTML entitet
		dec	oct	dec	oct	hex	7bit	dec	oct	hex	7bit	kar.	dec	oct	hex	kar.	Simb. ime	Simbol
Č	Caron	172	254	200	310	C8	H	200	310	C8	H	^	094	76	5E	È	Egrave	&Egrave;
č	caron	159	237	232	350	E8	h	232	350	E8	h	~	126	86	7E	è	egrave	&egrave;
Ć	Ccaron	143	217	198	306	C6	F	198	306	C6	F	]	093	75	5D	Æ	AElig	&AElig;
ć	ccaron	134	206	230	346	E6	f	230	346	E6	f	}	125	85	7D	æ	aelig	&aelig;
Đ	Dstroke	209	321	208	320	D0	P	208	320	D0	P	\	092	74	5C	Đ	Eth	&ETH;
đ	dstroke	208	320	240	360	F0	p	240	360	F0	p		124	84	7C	đ	eth	&eth;
Š	Scaron	230	346	<b>138</b>	<b>212</b>	<b>8A</b>	LF	<b>169</b>	<b>251</b>	<b>A9</b>	)	[	091	73	5B	©	copyright	&copy;
š	scaron	231	347	<b>154</b>	<b>232</b>	<b>9A</b>	SUB	<b>185</b>	<b>271</b>	<b>B9</b>	9	{	123	83	7B	¹	superscript 1	&sup1;
Ž	Zcaron	166	246	<b>142</b>	<b>216</b>	<b>8E</b>	SO	<b>174</b>	<b>256</b>	<b>AE</b>	.	@	064	52	40	®	registered trademark	&reg;
ž	zcaron	167	247	<b>158</b>	<b>236</b>	<b>9E</b>	RS	<b>190</b>	<b>276</b>	<b>BE</b>	>	`	096	78	60	¾	three quarters	&frac34;

Neki programi ili platforme pretvaraju (*stripaju*) 8-bitne kodove u 7-bitovne (označena sjenčano), ali se 4 HR znaka po Windows 1250 kodnoj stranici (š, ž, Š, Ž) pretvaraju u kontrolne kodove (**LF**, **SUB**, **SO** i **RS**) koji mogu omesti normalan rad na nekim računalnim platformama (Unix). Ista slova na platformama koje rabe ISO standard (Unix, Linux, Mac...) se pretvaraju u "bezopasne" znakove (, **9**, ., >). Kodovi su kako slijedi (u zagradama su tipkovničke kratice, no one su samo navedene kao reference i ne moraju vrijediti na svakoj platformi):

LF	Line Feed	(^J)
SUB	Substitute	(^Z)
SO	Shift Out	(^N)
RS	Record Separator	(^G ili ^^)